

S.Y.BAMM

C

Chapter - 17


- How Premier helps in Editing
- Understanding the Toolbar
- Important Files

ADD A FOOTER

The Main Tools


ADD A FOOTER

How To Import Your Media (5 Ways)




Experimenting with Video and Audio Layers

A




Right-click the video track header area.



Choose Add Track.



To add a single audio track, right-click the audio track header area and choose Add Track . Premiere Pro adds an audio track.




Right-click the audio track header area.


To delete a single video or audio track

To delete a single audio or video track, **D** right-click the track header **E** and choose Delete Track .






Right-click the track header area. Choose Add Tracks. Premiere Pro opens the Add Tracks dialog.





Choose the



number and placement of video tracks.

Specify the number,

placement, and track type for audio tracks .



Choose the number, placement, and track type for submix tracks.

Click OK to close the Add Tracks dialog and add the specified tracks

Standard: A standard track can have both stereo and mono audio tracks and is the default for new audio tracks. **Mono:** It includes an audio channel. If you leave a stereo file in a mono track, the stereo converts to mono,

5.1 : It includes only 5.1 surround sound tracks, consisting of three front audio channels (left, center and right); Two rear channels (left and right); And a low frequency subwoofer channel.

Adaptive: It can have mono or stereo tracks, and is used when you need to map source audio to different output channels.

Audio Submix Track: A synthetic track that contains no audio other than audio sent to submix from other audio tracks.

Master Audio Track: Controls the combined output of all tracks in the sequence, for example, you can adjust the overall track volume via a slider in the audio mixer.

To delete multiple tracks:

To delete multiple tracks do Right-click on the track header area and choose Delete Tracks Premiere Pro opens the Delete Tracks dialog.



Choose Delete Tracks to delete multiple tracks.


To delete video tracks, select the Delete Video Tracks check box and identify the tracks to delete in the associated drop-down menu.



Identify the video tracks to delete.

ADD A FOOTER

To delete audio tracks, select the Delete Audio Tracks check box and identify the tracks to delete in the associated drop-down menu



Identify the audio tracks to delete.

To delete audio submix tracks, select the Delete Audio Submix Tracks check box and identify the tracks to delete in the associated drop-down menu.

Click OK to close the Delete Tracks dialog and delete the specified tracks.

ADD A FOOTER

BASICS OF EDITING (CUT/LAYERS/DIFFERENT WINDOWS/ETC.):

